

Latest Features in Fixed-Point Designer


March 2016

R2016a

Auto Scaling Parameter Objects

Automatically propose and apply data types for parameter objects

- Proposals are based on design ranges when they are specified on the parameter object
 - In absence of design range on a tunable parameter object, it is inferred from blocks using the parameter
- Parameter objects defined in base/model workspace as well as data dictionary are supported




» ex_param_autoscale

fi Objects in Model Explorer

View and edit fi objects in Model Explorer


- View and edit fi objects and their local fimath properties using Model Explorer in Simulink
- Change the writable properties of fi objects from the Model Explorer



Simulation for Mixed Targets

Simulate system-level designs that integrate referenced models targeting an assembly of heterogeneous embedded devices


- Simulink models can now simulate system engineering level models that target multiple hardware devices
- For example, one referenced model can have device vendor configuration parameter set to 'ARM Compatible' and another referenced model set to 'ASIC/FPGA'



Fixed-Point Converter App Enhancements

Enhancements to language support and appearance of generated code in the Fixed-Point Converter app

- Support for arrays of structures
- Structures in generated fixed-point code
 - Proposes a unified data type for structures that are similar, no longer generating copies of structures
- Changes to fixed-point conversion code coverage
 - The app shows the coverage as a line execution count



The screenshot shows the Fixed-Point Converter app interface. The main window title is "Fixed-Point Converter - ex_2ndOrder_filter.prj". The top menu bar includes "Convert to Fixed Point", "SETTINGS", "SIMULATE", "DERIVE", "CONVERT", "TEST", and various tool icons. The "Source Code" tab is selected, displaying the MATLAB code for "ex_2ndOrder_filter_test.m". The code implements a second-order IIR filter. The code editor highlights line 11 with a green background, indicating it is the current line of execution. The "Function Replacements" table at the bottom shows the conversion of variables to fixed-point types. The table includes columns for Variable, Type, Sim Min, Sim Max, Static Min, Static Max, Whole N..., and Proposed Type. The "Input" variable x is converted to a 1x256 double with a range from -1 to 1, using numerictype(1, 16, 14). The "Output" variable y is converted to a 1x256 double with a range from -0.97 to 1.06, using numerictype(1, 16, 14). The "Persistent" variable z is converted to a 2x1 double with a range from -0.89 to 0.96, using numerictype(1, 16, 15). The "Local" variable is not explicitly listed in the table.

Variable	Type	Sim Min	Sim Max	Static Min	Static Max	Whole N...	Proposed Type
Input	1x256 d...	-1	1			No	numerictype(1, 16, 14)
Output	1x256 d...	-0.97	1.06			No	numerictype(1, 16, 14)
Persistent	2x1 do...	-0.89	0.96			No	numerictype(1, 16, 15)
Local							